
manila-ui Documentation

Release 12.0.0.0rc2.dev2

OpenStack Foundation

Sep 16, 2024

CONTENTS

1	Installation	1
1.1	Manual Installation	1
1.2	Installing Manila UI in RDO	1
2	Configuration	3
3	User Guide	5
3.1	Create a share	5
3.2	Delete a share	5
3.3	Allow access	6
3.4	Deny access	6
3.5	Edit share access metadata	6
3.6	Edit share metadata	6
3.7	Edit share	7
3.8	Resize share	7
3.9	Create share network	7
3.10	Delete a share network	8
3.11	Edit share network	8
3.12	Create security service	8
3.13	Delete a security service	9
3.14	Edit security service	9
4	Administrator Guide	11
4.1	Create a share type	11
4.2	Update share type	11
4.3	Delete share types	12
4.4	Delete shares	12
4.5	Delete share server	13
4.6	Delete share networks	13
5	Contributor Documentation	15
5.1	So You Want to Contribute	15
5.1.1	Bugs	15
5.1.2	Project Structure	15
5.2	Developing manila-ui	16
5.2.1	DevStack	16
5.2.2	Running unit tests	18
5.3	Adding New Features	18
5.4	Programming HowTos and Tutorials	19

5.4.1	Release Notes	19
	What are release notes?	19
	What needs a release note?	19
	What does not need a release note?	19
	How do I add a release note?	20
	Dos and Dents	21
	Examples	22

INSTALLATION

1.1 Manual Installation

Begin by installing Horizon following the [Horizon Manual Installation Guide](#) and clone Manila UI repository:

```
git clone https://opendev.org/openstack/manila-ui
```

Install Manila UI with all dependencies. From within the horizon folder:

```
pip install -e ../manila-ui/
```

And enable it in Horizon.:

```
cp ../manila-ui/manila_ui/local/enabled/*.py openstack_dashboard/local/  
↪enabled  
cp ../manila-ui/manila_ui/local/local_settings.d/_90_manila*.py openstack_  
↪dashboard/local/local_settings.d
```

1.2 Installing Manila UI in RDO

In order to install Manila UI in [RDO](#), please follow the steps below (you may need to use *sudo* privileges if you are not root):

```
# yum install -y openstack-manila-ui  
# systemctl restart httpd  
# systemctl restart memcached
```

Manila UI will now be available through OpenStack Horizon; look for the Shares tab under Project > Share. You can access Horizon with Manila UI using the same URL and port as before.

CONFIGURATION

It is possible to enable or disable some Manila UI features. To do so, look for files located in `manila_ui/local/local_settings.d/` directory, where you can redefine the values of the `OPENSTACK_MANILA_FEATURES` dict:

- `enable_share_groups`
- `enable_replication`
- `enable_migration`
- `enable_public_share_type_creation`
- `enable_public_share_group_type_creation`
- `enable_public_shares`
- `enabled_share_protocols`

By default, `enabled_share_protocols` within the `OPENSTACK_MANILA_FEATURES` dict contains a list with all the supported protocols. The operator can change this to display to users only those protocols that has been deployed and are available to use. E.g. if only NFS is available, the operator is expected to redefine `enabled_share_protocols` as follows:

```
OPENSTACK_MANILA_FEATURES = {  
    'enable_share_groups': True,  
    'enable_replication': True,  
    'enable_migration': True,  
    'enable_public_share_type_creation': True,  
    'enable_public_share_group_type_creation': True,  
    'enable_public_shares': True,  
    'enabled_share_protocols': ['NFS'],  
}
```


Shares are file storage that you provide access to instances. You can allow access to a share to a running instance or deny access to a share and allow access to it to another instance at any time. You can also delete a share. You can create snapshot from a share if the driver supports it. Only administrative users can create share types.

3.1 Create a share

1. Log in to the dashboard, choose a project, and click *Shares*.
2. Click *Create Share*.

In the dialog box that opens, enter or select the following values.

Share Name: Specify a name for the share.

Description: Optionally, provide a brief description for the share.

Share Type: Choose a share type.

Size (GB): The size of the share in gibibytes (GiB).

Share Protocol: Select NFS, CIFS, GlusterFS, or HDFS.

Share Network: Choose a share network.

Metadata: Enter metadata for the share creation if needed.

3. Click *Create Share*.

The dashboard shows the share on the *Shares* tab.

3.2 Delete a share

1. Log in to the dashboard, choose a project, and click *Shares*.
2. Select the check boxes for the shares that you want to delete.
3. Click *Delete Shares* and confirm your choice.

A message indicates whether the action was successful.

3.3 Allow access

1. Log in to the dashboard, choose a project, and click *Shares*.
2. Go to the share that you want to allow access and choose *Manage Rules* from Actions.
3. Click *Add rule*.

Access Type: Choose ip, user, or cert.

Access Level: Choose read-write or read-only.

Access To: Fill in Access To field.

4. Click *Add Rule*.

A message indicates whether the action was successful.

3.4 Deny access

1. Log in to the dashboard, choose a project, and click *Shares*.
2. Go to the share that you want to deny access and choose *Manage Rules* from Actions.
3. Choose the rule you want to delete.
4. Click *Delete rule* and confirm your choice.

A message indicates whether the action was successful.

3.5 Edit share access metadata

1. Log in to the dashboard, choose a project, and click *Shares*.
 2. Go to the share that you want to deny access and choose *Manage Rules* from Actions.
 3. Choose the rule you want to edit.
- #. Click *Edit Rule Metadata*: To add share access metadata, use key=value. To unset metadata, use key.

A message indicates whether the action was successful.

3.6 Edit share metadata

1. Log in to the dashboard, choose a project, and click *Shares*.
2. Go to the share that you want to edit and choose *Edit Share Metadata* from Actions.
3. *Metadata*: To add share metadata, use key=value. To unset metadata, use key.
4. Click *Edit Share Metadata*.

A message indicates whether the action was successful.

3.7 Edit share

1. Log in to the dashboard, choose a project, and click *Shares*.
2. Go to the share that you want to edit and choose *Edit Share* from Actions.
3. *Share Name*: Enter a new share name.
4. *Description*: Enter a new description.
5. Click *Edit Share*.

A message indicates whether the action was successful.

3.8 Resize share

1. Log in to the dashboard, choose a project, and click *Shares*.
2. Go to the share that you want to edit and choose *Resize Share* from Actions.
3. *New Size (GB)*: Enter new size. It can be increased or decreased from the original size. The size of the share cannot be lower than the size of the data stored in the share.

If increased, the size of the share will be extended. If decreased, the size of the share will be shrunked.
4. Click *Resize Share*.

A message indicates whether the action was successful.

3.9 Create share network

1. Log in to the dashboard, choose a project, click *Shares*, and click *Share Networks*.
2. Click *Create Share Network*.

In the dialog box that opens, enter or select the following values.

Name: Specify a name for the share network.

Description: Optionally, provide a brief description for the share network.

Neutron Net: Choose a neutron network.

Neutron Subnet: Choose a neutron subnet.

3. Click *Create Share Network*.

The dashboard shows the share network on the *Share Networks* tab.

3.10 Delete a share network

1. Log in to the dashboard, choose a project, click *Shares*, and click *Share Networks*.
2. Select the check boxes for the share networks that you want to delete.
3. Click *Delete Share Networks* and confirm your choice.

A message indicates whether the action was successful.

3.11 Edit share network

1. Log in to the dashboard, choose a project, click *Shares*, and click *Share Networks*.
2. Go to the share network that you want to edit and choose *Edit Share Network* from *Actions*.
3. *Name*: Enter a new share network name.
4. *Description*: Enter a new description.
5. Click *Edit Share Network*.

A message indicates whether the action was successful.

3.12 Create security service

1. Log in to the dashboard, choose a project, click *Shares*, and click *Security Services*.
2. Click *Create Security Service*.

In the dialog box that opens, enter or select the following values.

Name: Specify a name for the security service.

DNS IP: Enter the DNS IP address.

Server: Enter the server name.

Domain: Enter the domain name.

User: Enter the user name.

Password: Enter the password.

Confirm Password: Enter the password again to confirm.

Type: Choose the type from Active Directory, LDAP, or Kerberos.

Description: Optionally, provide a brief description for the security service.

3. Click *Create Security Service*.

The dashboard shows the security service on the *Security Services* tab.

3.13 Delete a security service

1. Log in to the dashboard, choose a project, click *Shares*, and click *Security Services*.
2. Select the check boxes for the security services that you want to delete.
3. Click *Delete Security Services* and confirm your choice.

A message indicates whether the action was successful.

3.14 Edit security service

1. Log in to the dashboard, choose a project, click *Shares*, and click *Security Services*.
2. Go to the security service that you want to edit and choose *Edit Security Service* from Actions.
3. *Name*: Enter a new security service name.
4. *Description*: Enter a new description.
5. Click *Edit Security Service*.

A message indicates whether the action was successful.

ADMINISTRATOR GUIDE

Shares are file storage that instances can access. Users can allow or deny a running instance to have access to a share at any time. For information about using the Dashboard to create and manage shares as an end user, see the *User Guide*.

As an administrative user, you can manage shares and share types for users in various projects. You can create and delete share types, and view or delete shares.

4.1 Create a share type

1. Log in to the Dashboard and choose the *admin* project from the drop-down list.
2. On the *Admin* tab, open the *System* tab and click the *Shares* category.
3. Click the *Share Types* tab, and click *Create Share Type* button. In the *Create Share Type* window, enter or select the following values.

Name: Enter a name for the share type.

Driver handles share servers: Choose True or False

Extra specs: To add extra specs, use key=value.

4. Click *Create Share Type* button to confirm your changes.

Note

A message indicates whether the action succeeded.

4.2 Update share type

1. Log in to the Dashboard and choose the *admin* project from the drop-down list.
2. On the *Admin* tab, open the *System* tab and click the *Shares* category.
3. Click the *Share Types* tab, select the share type that you want to update.
4. Select *Update Share Type* from Actions.
5. In the *Update Share Type* window, update extra specs.

Extra specs: To add extra specs, use `key=value`. To unset extra specs, use `key`. *Name*: To update share type name. *Description*: To update share type description. *Public*: To update share type visibility.

6. Click *Update Share Type* button to confirm your changes.

Note

A message indicates whether the action succeeded.

4.3 Delete share types

When you delete a share type, shares of that type are not deleted.

1. Log in to the Dashboard and choose the *admin* project from the drop-down list.
2. On the *Admin* tab, open the *System* tab and click the *Shares* category.
3. Click the *Share Types* tab, select the share type or types that you want to delete.
4. Click *Delete Share Types* button.
5. In the *Confirm Delete Share Types* window, click the *Delete Share Types* button to confirm the action.

Note

A message indicates whether the action succeeded.

4.4 Delete shares

1. Log in to the Dashboard and choose the *admin* project from the drop-down list.
2. On the *Admin* tab, open the *System* tab and click the *Shares* category.
3. Select the share or shares that you want to delete.
4. Click *Delete Shares* button.
5. In the *Confirm Delete Shares* window, click the *Delete Shares* button to confirm the action.

Note

A message indicates whether the action succeeded.

4.5 Delete share server

1. Log in to the Dashboard and choose the *admin* project from the drop-down list.
2. On the *Admin* tab, open the *System* tab and click the *Share Servers* category.
3. Select the share that you want to delete.
4. Click *Delete Share Server* button.
5. In the *Confirm Delete Share Server* window, click the *Delete Share Server* button to confirm the action.

Note

A message indicates whether the action succeeded.

4.6 Delete share networks

1. Log in to the Dashboard and choose the *admin* project from the drop-down list.
2. On the *Admin* tab, open the *System* tab and click the *Share Networks* category.
3. Select the share network or share networks that you want to delete.
4. Click *Delete Share Networks* button.
5. In the *Confirm Delete Share Networks* window, click the *Delete Share Networks* button to confirm the action.

Note

A message indicates whether the action succeeded.

CONTRIBUTOR DOCUMENTATION

5.1 So You Want to Contribute

For general information on contributing to OpenStack, please check out the [contributor guide](#) to get started. It covers all the basics that are common to all OpenStack projects: the accounts you need, the basics of interacting with our Gerrit review system, how we communicate as a community, etc.

This project contains a plug-in to the OpenStack Dashboard (Horizon). It adds functionality to the OpenStack Dashboard to interact with [Manila](#), the OpenStack Shared File Systems service. Refer to the [Contributor guide for Manila](#) for information regarding the teams task trackers, communicating with other project developers and contacting the core team.

See [Developing manila-ui](#) for details about how to bootstrap a development environment and test manila-ui.

5.1.1 Bugs

You found an issue and want to make sure we are aware of it? You can do so on [Launchpad](#).

If you're looking to contribute, search for the [low-hanging-fruit](#) tag to see issues that are easier to get started with.

5.1.2 Project Structure

This project includes two dashboard components:

- [administrator dashboard](#)
- [user dashboard](#)

The administrator dashboard extends the OpenStack Dashboards administrator interface by adding [Share](#) (short for [Shared File Systems](#)) functionality to manage [Share](#) and [Share Group Types](#), [Share servers](#) and other *administrator-only* components of the [Shared File System](#) service. It also extends the functionality of the [Identity](#) service to allow controlling [Shared File System](#) service quotas.

The [User](#) dashboard provides all user facing functionality.

5.2 Developing manila-ui

For simple documentation and code fixes, you dont need a comprehensive test environment with this projects main dependencies such as manila, python-manilaclient and horizon. Before submitting any code fixes for review, you can run *Running unit tests* locally. To try your changes with manila-ui and Horizon and all other dependencies, we recommend the use of DevStack.

5.2.1 DevStack

DevStack can help you setup a simple development environment for developing and testing manila-ui. Read the section about DevStack in the [manila contributor guide](#).

Note

We absolutely recommend using a fake shared file system back end as opposed to a real storage system to experience the full capabilities of manila UI. Manila UI is built with the assumption that all APIs manila exposes are usable. In reality, different real world storage back ends have [different capabilities](#) and this project doesnt need to worry about them to provide a general purpose graphical user interface to Manila. A fake driver provides fake storage, so dont expect to be able to mount or use the shared file systems that you create with it.

You can use the following local.conf file to configure DevStack including Manila and manila-ui using a few fake back ends:

```
[[local|localrc]]

# auth
ADMIN_PASSWORD=nomoresecret
DATABASE_PASSWORD=$ADMIN_PASSWORD
RABBIT_PASSWORD=$ADMIN_PASSWORD
SERVICE_PASSWORD=$ADMIN_PASSWORD

# enable logging for DevStack
LOGFILE=/opt/stack/logs/stack.sh.log

# Logging mode for DevStack services
VERBOSE=True

# manila
enable_plugin manila https://opendev.org/openstack/manila

# manila-ui
enable_plugin manila-ui https://opendev.org/openstack/manila-ui

# python-manilaclient
LIBS_FROM_GIT=python-manilaclient

# share driver
SHARE_DRIVER=manila.tests.share.drivers.dummy.DummyDriver
```

(continues on next page)

(continued from previous page)

```
# share types
MANILA_DEFAULT_SHARE_TYPE_EXTRA_SPECS='snapshot_support=True create_share_
↪from_snapshot_support=True revert_to_snapshot_support=True mount_snapshot_
↪support=True'
MANILA_CONFIGURE_DEFAULT_TYPES=True

# backends and groups
MANILA_ENABLED_BACKENDS=alpha,beta,gamma,delta
MANILA_CONFIGURE_GROUPS=alpha,beta,gamma,delta,membernet,adminnet

# alpha
MANILA_OPTGROUP_alpha_share_driver=manila.tests.share.drivers.dummy.
↪DummyDriver
MANILA_OPTGROUP_alpha_driver_handles_share_servers=True
MANILA_OPTGROUP_alpha_share_backend_name=ALPHA
MANILA_OPTGROUP_alpha_network_config_group=membernet
MANILA_OPTGROUP_alpha_admin_network_config_group=adminnet

# beta
MANILA_OPTGROUP_beta_share_driver=manila.tests.share.drivers.dummy.DummyDriver
MANILA_OPTGROUP_beta_driver_handles_share_servers=True
MANILA_OPTGROUP_beta_share_backend_name=BETA
MANILA_OPTGROUP_beta_network_config_group=membernet
MANILA_OPTGROUP_beta_admin_network_config_group=adminnet

# gamma
MANILA_OPTGROUP_gamma_share_driver=manila.tests.share.drivers.dummy.
↪DummyDriver
MANILA_OPTGROUP_gamma_driver_handles_share_servers=False
MANILA_OPTGROUP_gamma_share_backend_name=GAMMA
MANILA_OPTGROUP_gamma_replication_domain=DUMMY_DOMAIN

# delta
MANILA_OPTGROUP_delta_share_driver=manila.tests.share.drivers.dummy.
↪DummyDriver
MANILA_OPTGROUP_delta_driver_handles_share_servers=False
MANILA_OPTGROUP_delta_share_backend_name=DELTA
MANILA_OPTGROUP_delta_replication_domain=DUMMY_DOMAIN

# membernet
MANILA_OPTGROUP_membernet_network_api_class=manila.network.standalone_network_
↪plugin.StandaloneNetworkPlugin
MANILA_OPTGROUP_membernet_standalone_network_plugin_gateway=10.0.0.1
MANILA_OPTGROUP_membernet_standalone_network_plugin_mask=24
MANILA_OPTGROUP_membernet_standalone_network_plugin_network_type=vlan
MANILA_OPTGROUP_membernet_standalone_network_plugin_segmentation_id=1010
MANILA_OPTGROUP_membernet_standalone_network_plugin_allowed_ip_ranges=10.0.0.
↪10-10.0.0.209
```

(continues on next page)

(continued from previous page)

```
MANILA_OPTGROUP_membernet_network_plugin_ipv4_enabled=True

# adminnet
MANILA_OPTGROUP_adminnet_network_api_class=manila.network.standalone_network_
↪plugin.StandaloneNetworkPlugin
MANILA_OPTGROUP_adminnet_standalone_network_plugin_gateway=11.0.0.1
MANILA_OPTGROUP_adminnet_standalone_network_plugin_mask=24
MANILA_OPTGROUP_adminnet_standalone_network_plugin_network_type=vlan
MANILA_OPTGROUP_adminnet_standalone_network_plugin_segmentation_id=1011
MANILA_OPTGROUP_adminnet_standalone_network_plugin_allowed_ip_ranges=11.0.0.
↪10-11.0.0.19,11.0.0.30-11.0.0.39,11.0.0.50-11.0.0.199
MANILA_OPTGROUP_adminnet_network_plugin_ipv4_enabled=True
```

Once your DevStack is ready, you can log into the OpenStack Dashboard and explore the Share dashboards under *Project* and *Admin* sections that are included due to manila-ui.

See the [Horizon user guide](#) for instructions regarding logging into the OpenStack Dashboard.

5.2.2 Running unit tests

The unit tests can be executed directly from within this Manila UI plugin project directory by using:

```
$ cd ../manila-ui
$ tox
```

This is made possible by the dependency in `test-requirements.txt` upon the horizon source, which pulls down all of the horizon and `openstack_dashboard` modules that the plugin uses.

To run only py3 unit tests, use following command:

```
$ tox -e py3
```

To run unit tests using specific Django version use the following:

```
$ tox -e py3-dj22
$ tox -e py3-dj110
```

5.3 Adding New Features

When implementing a new feature, you may think about making it optional, so it could be enabled or disabled in different deployments.

How to use it:

```
from django.conf import settings
manila_config = getattr(settings, 'OPENSTACK_MANILA_FEATURES', {})
manila_config.get('your_new_config_option', 'value_of_config_option')
```

See [Configuration](#) section for more configuration details.

It is also expected that each addition of new logic to Manila UI is covered by unit tests.

Test modules should be located under `manila_ui/tests`, satisfying the following template when tests are written for a specific module:

```
manila_ui[/tests]/path/to/[test_]module_name.py
```

However, when testing the flow between different modules (using test app), the tests can be added to a test module that can satisfy the following template:

```
manila_ui/tests/path/to/directory/tests.py
```

Manila UI tests use the `mock` module from the `unittest` package for unit testing.

5.4 Programming HowTos and Tutorials

5.4.1 Release Notes

What are release notes?

Release notes are important for change management within manila. Since manila follows a release cycle with milestones, release notes provide a way for the community and users to quickly grasp what changes occurred within a development milestone. To the OpenStack release management and documentation teams, release notes are a way to compile changes per milestone. These notes are published on the [OpenStack Releases website](#). Automated tooling is built around `releasenotes` and they get appropriately handled per release milestone, including any back-ports to stable releases.

What needs a release note?

- Changes that impact an upgrade, most importantly, those that require a deployer to take some action while upgrading
- A new feature is implemented
- An existing feature is deprecated
- An existing feature is removed
- Behavior of an existing feature has changed in a discernible way to an end user or administrator
- A security bug is fixed
- New configuration option is added

What does not need a release note?

- A code change that doesn't change the general behavior of any feature such as code refactor or logging changes.
- Functional or unit test coverage enhancement
- Changes to the content of an error message displayed on the UI
- Any change submitted with a justified `TrivialFix` flag added in the commit message
- Adding or changing documentation within in-tree documentation guides

How do I add a release note?

We use [Reno](#) to create and manage release notes. The new subcommand combines a random suffix with a slug value to make the new file with a unique name that is easy to identify again later. To create a release note for your change, use:

```
$ reno new slug-goes-here
```

If reno is not installed globally on your system, you can use a tox environment in manila:

```
$ tox -e newnote slug-goes-here
```

Note

When you are adding a bug-fix reno, name your file using the template: bug-<launchpad-bug-id>-slug-goes-here.

Then add the notes in yaml format in the file created. Pay attention to the type of section. The following are general sections to use:

prelude

General comments about the change. The prelude from all notes in a release are combined, in note order, to produce a single prelude introducing the release.

features

New features introduced

issues

A list of known issues with respect to the change being introduced. For example, if the new feature in the change is experimental or known to not work in some cases, it should be mentioned here.

upgrade

A list of upgrade notes in the release. Any removals that affect upgrades are to be noted here.

deprecations

Any features, APIs, configuration options that the change has deprecated. Deprecations are not removals. Deprecations suggest that there will be support for a certain timeline. Deprecation should allow time for users to make necessary changes for the removal to happen in a future release. It is important to note the timeline of deprecation in this section.

critical

A list of *fixed* critical bugs (descriptions only).

security

A list of *fixed* security issues (descriptions only).

fixes

A list of other *fixed* bugs (descriptions only).

other

Other notes that are important but do not fall into any of the given categories.

```
---
prelude: >
    Replace this text with content to appear at the
    top of the section for this change.
features:
- List new features here, or remove this section.
issues:
- List known issues here, or remove this section.
upgrade:
- List upgrade notes here, or remove this section.
deprecations:
- List deprecation notes here, or remove this section
critical:
- Add critical notes here, or remove this section.
security:
- Add security notes here, or remove this section.
fixes:
- Add normal bug fixes here, or remove this section.
other:
- Add other notes here, or remove this section.
```

Dos and Donts

- Release notes need to be succinct. Short and unambiguous descriptions are preferred
- Write in past tense, unless you are writing an imperative statement
- Do not have blank sections in the file
- Do not include code or links
- Avoid special rst formatting unless absolutely necessary
- Always prefer including a release note in the same patch
- Release notes are not a replacement for developer/user/admin documentation
- Release notes are not a way of conveying behavior of any features or usage of any APIs
- Limit a release note to fewer than 2-3 lines per change per section
- OpenStack prefers atomic changes. So remember that your change may need the fewest sections possible
- General writing guidelines can be found [here](#)
- Proofread your note. Pretend you are a user or a deployer who is reading the note after a milestone or a release has been cut

Examples

The following need only be considered as directions for formatting. They are **not** fixes or features in manila.

- *add-share-network-create-workflows-41cad17c1498a3.yaml*

```
---  
features:  
- switched share network creation into two-step workflows.
```